

## How To Resize ext3 Partitions Without Losing Data

*By Falko Timme*

Published: 2007-01-07 17:12

# How To Resize ext3 Partitions Without Losing Data

Version 1.0

Author: Falko Timme <ft [at] falkotimme [dot] com>

Last edited 12/31/2006

This article is about resizing ext3 partitions without losing data. It shows how to shrink and enlarge existing ext3 partitions and how to merge two ext3 partitions. This can be quite useful if you do not use LVM and you realize that your existing partitioning does not meet your actual needs anymore.

There are many ways of achieving this goal but this is the way I take. I do not issue any guarantee that this will work for you!

## 1 Preliminary Note

(I run all the commands in this tutorial as the root user, so make sure you're logged in as root. If you are on a Ubuntu system, you can become root like this:

```
sudo su
```

)

I have tested this on a Ubuntu Edgy Eft desktop system that has all files in one large partition (around 10 GB, device `/dev/sda1`). The partitioning looks like this:

```
df -h
```

<i>Filesystem</i>	<i>Size</i>	<i>Used</i>	<i>Avail</i>	<i>Use%</i>	<i>Mounted on</i>
<code>/dev/sda1</code>	<code>9.5G</code>	<code>4.1G</code>	<code>4.9G</code>	<code>46%</code>	<code>/</code>

```

varrun          94M  132K   94M   1% /var/run
varlock        94M    0   94M   0% /var/lock
udev           10M   52K   10M   1% /dev
devshm         94M    0   94M   0% /dev/shm
lrm            94M   18M   77M  19% /lib/modules/2.6.17-10-generic/volatile

```

The partition that is to be resized must be unmounted when we do the resizing; obviously this is not possible if this is the partition that holds all important system files like in this example. Therefore we download a Live Linux-CD such as [Knoppix](#) from which we boot later on (if you have physical access to the system). If it is a remote system that you don't have physical access to, you need a rescue system on that system (a lot of hosting companies offer dedicated servers with rescue systems nowadays) that you can boot into (instead of Knoppix), and this rescue system must have the following tools: *fdisk*, *umount*, *fsck*, *tune2fs*, *e2fsck*, *resize2fs*.

If the partition that you want to resize doesn't hold any system files (such as */home* partitions, partitions for backups, etc.), you don't need a Knoppix Live-CD or a rescue system, because all steps can be run from the original system.

If you want to resize partitions on production systems, please back up your data before, because it is possible you lose all your data if you don't calculate the size of your new partition correctly (especially when shrinking a partition)! You have been warned! Tutorials about backups can be found here: [http://www.howtoforge.com/taxonomy\\_menu/1/34](http://www.howtoforge.com/taxonomy_menu/1/34)

I'm going to resize */dev/sda1* in this tutorial. If your partition is named differently, please replace */dev/sda1* with your own device (e.g. */dev/hda5*, */dev/sdb3*, etc.).

## 2 Shrinking An ext3 Partition

This chapter is about shrinking an ext3 partition. I want to shrink */dev/sda1* in this example. First we gather some details on our original system:

```
df
```

```

Filesystem      1K-blocks      Used Available Use% Mounted on
/dev/sda1       9859036      4234908   5123304  46% /
varrun          95480         132     95348    1% /var/run
varlock         95480          0     95480    0% /var/lock

```

```
udev                10240         52    10188    1% /dev
devshm              95480         0    95480    0% /dev/shm
lrm                 95480    17580    77900   19% /lib/modules/2.6.17-10-generic/volatile
```

```
df -B 4k
```

```
Filesystem          4K-blocks      Used Available Use% Mounted on
/dev/sda1           2464759    1058727  1280826  46% /
varrun              23870         33    23837    1% /var/run
varlock             23870         0    23870    0% /var/lock
udev                2560         13    2547    1% /dev
devshm              23870         0    23870    0% /dev/shm
lrm                 23870     4395    19475   19% /lib/modules/2.6.17-10-generic/volatile
```

```
df -h
```

```
Filesystem          Size  Used Avail Use% Mounted on
/dev/sda1           9.5G  4.1G  4.9G  46% /
varrun              94M  132K   94M   1% /var/run
varlock             94M    0   94M   0% /var/lock
udev                10M   52K   10M   1% /dev
devshm              94M    0   94M   0% /dev/shm
lrm                 94M   18M   77M  19% /lib/modules/2.6.17-10-generic/volatile
```

```
fdisk -l
```

```
Disk /dev/sda: 10.7 GB, 10737418240 bytes
255 heads, 63 sectors/track, 1305 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
```

<i>Device</i>	<i>Boot</i>	<i>Start</i>	<i>End</i>	<i>Blocks</i>	<i>Id</i>	<i>System</i>
<i>/dev/sda1</i>	<i>*</i>	<i>1</i>	<i>1247</i>	<i>10016496</i>	<i>83</i>	<i>Linux</i>
<i>/dev/sda2</i>		<i>1248</i>	<i>1305</i>	<i>465885</i>	<i>5</i>	<i>Extended</i>
<i>/dev/sda5</i>		<i>1248</i>	<i>1305</i>	<i>465853+</i>	<i>82</i>	<i>Linux swap / Solaris</i>

```
fdisk -s /dev/sda1
```

10016496

Then we shut down the system and boot into our Knoppix Live-CD (or your rescue system) (if the partition you want to resize doesn't hold any system files, you can do everything from the original system; the steps are the same, just omit booting into Knoppix/your rescue system).

```
shutdown -r now
```

After Knoppix has booted, open a terminal and become root by running

```
su
```

*/dev/sda1* should be unmounted by default, but you can run

```
umount /dev/sda1
```

to go sure.

Then run

```
fscck -n /dev/sda1
```

The output looks like this:

```
fsck 1.38 (30-Jun-2005)
 e2fsck 1.38 (30-Jun-2005)
/dev/sda1: clean, 159037/1254176 files, 1095299/2504124 blocks
```

Next we remove the journal from `/dev/sda1`, thus turning it into an ext2 partition:

```
tune2fs -O ^has_journal /dev/sda1
```

The output looks like this:

```
tune2fs 1.38 (30-Jun-2005)
```

Then run

```
e2fsck -f /dev/sda1
```

```
e2fsck 1.38 (30-Jun-2005)
 Pass 1: Checking inodes, blocks, and sizes
 Pass 2: Checking directory structure
 Pass 3: Checking directory connectivity
 Pass 4: Checking reference counts
 Pass 5: Checking group summary information
/dev/sda1: 164178/1254176 files (0.6% non-contiguous), 1051617/2504124 blocks
```

Now we resize our file system with `resize2fs`. `resize2fs` can resize ext2 file systems, but not ext3 file systems, that's why we had to turn `/dev/sda1` to ext2. Currently, 4.1GB are used on `/dev/sda1` (see the `df -h` output above), So it's safe to shrink it from 10GB to about 6GB (if you make it smaller than 4.1GB, you will lose data!). Therefore we run

```
resize2fs /dev/sda1 6000M
```

The output is as follows:

```
resize2fs 1.38 (30-Jun-2005)
  Resizing the filesystem on /dev/sda1 to 1536000 (4k) blocks.
The filesystem on /dev/sda1 is now 1536000 blocks long.
```

Please take note of the amount of blocks (1536000) and their size (4k). We need that soon.

Now we delete our `/dev/sda1` partition (don't be afraid, no data will be lost) and create a new, smaller one (but still big enough to hold our resized file system!). We can do this with `fdisk`:

```
fdisk /dev/sda
```

(Yes, it's `/dev/sda`, not `/dev/sda1`.)

The number of cylinders for this disk is set to 1305.  
There is nothing wrong with that, but this is larger than 1024,  
and could in certain setups cause problems with:  
1) software that runs at boot time (e.g., old versions of LILO)  
2) booting and partitioning software from other OSs  
(e.g., DOS FDISK, OS/2 FDISK)

Type `m` to get a list of all commands:

```
Command (m for help): m
Command action
  a  toggle a bootable flag
  b  edit bsd disklabel
  c  toggle the dos compatibility flag
  d  delete a partition
  l  list known partition types
  m  print this menu
```

```
n  add a new partition
o  create a new empty DOS partition table
p  print the partition table
q  quit without saving changes
s  create a new empty Sun disklabel
t  change a partition's system id
u  change display/entry units
v  verify the partition table
w  write table to disk and exit
x  extra functionality (experts only)
```

Now we delete partition no. 1 (*/dev/sda1*):

```
Command (m for help): d
Partition number (1-5): 1
```

Next we create a new */dev/sda1* partition. It was a primary partition before, so we choose *p* again, and again it is our partition no. 1:

```
Command (m for help): n
Command action
  l  logical (5 or over)
  p  primary partition (1-4)
p
Partition number (1-4): 1
```

Now comes the crucial part - we are asked about the size of the new partition. The first cylinder is no problem, it is the one from the *fdisk -l* output at the beginning of this chapter (1).

```
First cylinder (1-1305, default 1): 1
```

But we don't have a value for the last cylinder of our new partition. Fortunately, we can specify the size in kilobytes (*K*), so we calculate the size like this:

We multiply the amount of blocks from the *resize2fs* output (1536000) by the size of a block (4k), and to go sure the partition is big enough, we add 3 to

5% to it (3% was enough for me, but if you want to go sure take 5%):

1536000 \* 4k \* 1.03 = 6328320k

So we prepend that value with a + sign and replace the small *k* with a capital one (*K*) and enter it:

```
Last cylinder or +size or +sizeM or +sizeK (1-1247, default 1247): +6328320K
```

Our original `/dev/sda1` had the bootable flag (see the `fdisk -l` output from the beginning of this chapter), so we must add it to our new `/dev/sda1` again:

```
Command (m for help): a
Partition number (1-5): 1
```

Now let's write our new partition table and exit `fdisk`:

```
Command (m for help): w
The partition table has been altered!
```

```
Calling ioctl() to re-read partition table.
```

```
WARNING: Re-reading the partition table failed with error 16: Device or resource busy.
The kernel still uses the old table.
The new table will be used at the next reboot.
Syncing disks.
```

Now we reboot the system, and again we boot into our Knoppix system (rescue system; original system if resized partition doesn't hold system files):

```
shutdown -r now
```

Become root again (on Knoppix run

```
su
```



)

and then run this:

```
fsck -n /dev/sda1
```

The output should look like this:

```
fsck 1.38 (30-Jun-2005)
  e2fsck 1.38 (30-Jun-2005)
/dev/sda1: clean, 159036/765536 files, 1047239/1536000 blocks
```

Then we create the journal on our new `/dev/sda1`, thus turning it into an ext3 partition again:

```
tune2fs -j /dev/sda1
```

```
tune2fs 1.38 (30-Jun-2005)
  Creating journal inode: done
  This filesystem will be automatically checked every 30 mounts or
  0 days, whichever comes first. Use tune2fs -c or -i to override.
```

Now we are done. Shut down the system and boot into the \_\_\_\_\_ :

```
shutdown -r now
```

If everything goes well, the original system will boot up, and no data has been lost. Now we can gather some details about our new partitioning and compare them with the information we collected at the beginning of this chapter:

```
df
```

```

Filesystem      1K-blocks      Used Available Use% Mounted on
/dev/sda1        6047868    4224140   1639408  73% /
varrun           95480         132    95348   1% /var/run
varlock          95480          0    95480   0% /var/lock
udev             10240          52    10188   1% /dev
devshm           95480          0    95480   0% /dev/shm
lrm              95480    17580    77900  19% /lib/modules/2.6.17-10-generic/volatile

```

```
df -B 4k
```

```

Filesystem      4K-blocks      Used Available Use% Mounted on
/dev/sda1       1511967    1056035   409852  73% /
varrun          23870         33    23837   1% /var/run
varlock         23870          0    23870   0% /var/lock
udev            2560          13    2547   1% /dev
devshm          23870          0    23870   0% /dev/shm
lrm             23870    4395    19475  19% /lib/modules/2.6.17-10-generic/volatile

```

```
df -h
```

```

Filesystem      Size  Used Avail Use% Mounted on
/dev/sda1       5.8G  4.1G  1.6G  73% /
varrun          94M  132K  94M   1% /var/run
varlock         94M    0  94M   0% /var/lock
udev            10M   52K  10M   1% /dev
devshm          94M    0  94M   0% /dev/shm
lrm             94M   18M  77M  19% /lib/modules/2.6.17-10-generic/volatile

```

```
fdisk -l
```

```
Disk /dev/sda: 10.7 GB, 10737418240 bytes
255 heads, 63 sectors/track, 1305 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
```

```
Device Boot      Start          End      Blocks   Id  System
/dev/sda1  *            1           789     6337611   83  Linux
/dev/sda2                1248        1305       465885    5  Extended
/dev/sda5                1248        1305     465853+   82  Linux swap / Solaris
```

```
fdisk -s /dev/sda1
```

```
6337611
```

### 3 Enlarging An ext3 Partition

In this example we have a `/dev/sda1` partition with about 6GB of size, and right behind that partition we have about 4GB of unused space. We want to add those 4GB of unused space to our `/dev/sda1` partition (this doesn't work if these 4GB don't come right behind our `/dev/sda1` partition, but are elsewhere on the hard disk!).

First, we collect some details again about our current partitioning:

```
df
```

```
Filesystem      1K-blocks      Used Available Use% Mounted on
/dev/sda1        6047868    4224140   1639408  73% /
varrun           95480         132    95348  1% /var/run
varlock          95480          0    95480  0% /var/lock
udev             10240          52    10188  1% /dev
devshm           95480          0    95480  0% /dev/shm
lrm              95480       17580    77900  19% /lib/modules/2.6.17-10-generic/volatile
```

```
df -B 4k
```

Filesystem	4K-blocks	Used	Available	Use%	Mounted on
/dev/sda1	1511967	1056035	409852	73%	/
varrun	23870	33	23837	1%	/var/run
varlock	23870	0	23870	0%	/var/lock
udev	2560	13	2547	1%	/dev
devshm	23870	0	23870	0%	/dev/shm
lrm	23870	4395	19475	19%	/lib/modules/2.6.17-10-generic/volatile

```
df -h
```

Filesystem	Size	Used	Avail	Use%	Mounted on
/dev/sda1	5.8G	4.1G	1.6G	73%	/
varrun	94M	132K	94M	1%	/var/run
varlock	94M	0	94M	0%	/var/lock
udev	10M	52K	10M	1%	/dev
devshm	94M	0	94M	0%	/dev/shm
lrm	94M	18M	77M	19%	/lib/modules/2.6.17-10-generic/volatile

```
fdisk -l
```

```
Disk /dev/sda: 10.7 GB, 10737418240 bytes
255 heads, 63 sectors/track, 1305 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
```

Device	Boot	Start	End	Blocks	Id	System
/dev/sda1	*	1	789	6337611	83	Linux
/dev/sda2		1248	1305	465885	5	Extended

```
/dev/sda5          1248          1305          465853+  82  Linux swap / Solaris
```

```
fdisk -s /dev/sda1
```

```
6337611
```

Then we shut down the system and boot into our Knoppix Live-CD (or your rescue system) (if the partition you want to resize doesn't hold any system files, you can do everything from the original system; the steps are the same, just omit booting into Knoppix/your rescue system).

```
shutdown -r now
```

After Knoppix has booted, open a terminal and become root by running

```
su
```

`/dev/sda1` should be unmounted by default, but you can run

```
umount /dev/sda1
```

to go sure.

Then run

```
fscck -n /dev/sda1
```

```
fscck 1.38 (30-Jun-2005)
```

```
e2fscck 1.38 (30-Jun-2005)
```

```
/dev/sda1: clean, 159036/765536 files, 1080014/1536000 blocks
```

Next we remove the journal from `/dev/sda1`, thus turning it into an ext2 partition:

```
tune2fs -O ^has_journal /dev/sda1
```

The output looks like this:

```
tune2fs 1.38 (30-Jun-2005)
```

Now we use `fdisk` to delete our current `/dev/sda1` partition and create a bigger one (don't be afraid, no data will be lost):

```
fdisk /dev/sda
```

(Yes, it's `/dev/sda`, not `/dev/sda1`.)

*The number of cylinders for this disk is set to 1305.*

*There is nothing wrong with that, but this is larger than 1024, and could in certain setups cause problems with:*

- 1) software that runs at boot time (e.g., old versions of LILO)*
- 2) booting and partitioning software from other OSs (e.g., DOS FDISK, OS/2 FDISK)*

Type `m` to get a list of all commands:

*Command (m for help): m*

*Command action*

- a toggle a bootable flag*
- b edit bsd disklabel*
- c toggle the dos compatibility flag*
- d delete a partition*
- l list known partition types*
- m print this menu*

```
n  add a new partition
o  create a new empty DOS partition table
p  print the partition table
q  quit without saving changes
s  create a new empty Sun disklabel
t  change a partition's system id
u  change display/entry units
v  verify the partition table
w  write table to disk and exit
x  extra functionality (experts only)
```

Let's print out the partition table:

Command (m for help): p

```
Disk /dev/sda: 10.7 GB, 10737418240 bytes
255 heads, 63 sectors/track, 1305 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
```

Device	Boot	Start	End	Blocks	Id	System
/dev/sda1	*	1	789	6337611	83	Linux
/dev/sda2		1248	1305	465885	5	Extended
/dev/sda5		1248	1305	465853+	82	Linux swap / Solaris

Now we delete partition no. 1 (/dev/sda1):

```
Command (m for help): d
Partition number (1-5): 1
```

Next we create a new /dev/sda1 partition. It was a primary partition before, so we choose *p* again, and again it is our partition no. 1:

```
Command (m for help): n
Command action
```

```
l   logical (5 or over)
p   primary partition (1-4)
p
Partition number (1-4): 1
```

Now we must specify the first and the last cylinder of our new `/dev/sda1` partition. We know the first cylinder, can can take it from the `fdisk -l` output before:

```
First cylinder (1-1305, default 1): 1
```

Now `fdisk` tells us the highest possible cylinder of our new partition (1247 in this example), so we simply enter this number:

```
Last cylinder or +size or +sizeM or +sizeK (1-1247, default 1247): 1247
```

Let's print out our new partition table:

```
Command (m for help): p
```

```
Disk /dev/sda: 10.7 GB, 10737418240 bytes
255 heads, 63 sectors/track, 1305 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
```

Device	Boot	Start	End	Blocks	Id	System
/dev/sda1		1	1247	10016496	83	Linux
/dev/sda2		1248	1305	465885	5	Extended
/dev/sda5		1248	1305	465853+	82	Linux swap / Solaris

Our original `/dev/sda1` had the bootable flag (see the `fdisk -l` output from the beginning of this chapter), so we must add it to our new `/dev/sda1` again:

```
Command (m for help): a
Partition number (1-5): 1
```

Now let's write our new partition table and exit `fdisk`:



Command (m for help): w

*The partition table has been altered!*

Calling `ioctl()` to re-read partition table.

*WARNING: Re-reading the partition table failed with error 16: Device or resource busy.*

*The kernel still uses the old table.*

*The new table will be used at the next reboot.*

*Syncing disks.*

Now we reboot the system, and again we boot into our Knoppix system (rescue system; original system if resized partition doesn't hold system files):

```
shutdown -r now
```

Become root again (on Knoppix run

```
su
```

)

Then run

```
e2fsck -f /dev/sda1
```

Now we must resize the file system in our `/dev/sda1` partition. If we don't specify a size for the `resize2fs` command, it will assume the biggest possible size so we don't have to calculate. So we run

```
resize2fs /dev/sda1
```

The output looks like this:

```
resize2fs 1.38 (30-Jun-2005)
  Resizing the filesystem on /dev/sda1 to 2504124 (4k) blocks.
The filesystem on /dev/sda1 is now 2504124 blocks long.
```

Next we run

```
fck -n /dev/sda1
```

```
fck 1.38 (30-Jun-2005)
  e2fck 1.38 (30-Jun-2005)
/dev/sda1: clean, 159036/1254176 files, 1062544/2504124 blocks
```

and create the journal on `/dev/sda1`, thus turning it into an ext3 partition again:

```
tune2fs -j /dev/sda1
```

```
tune2fs 1.38 (30-Jun-2005)
  Creating journal inode: done
  This filesystem will be automatically checked every 30 mounts or
  0 days, whichever comes first. Use tune2fs -c or -i to override.
```

Now we are done. Shut down the system and boot into the :

```
shutdown -r now
```

If everything goes well, the original system will boot up, and no data has been lost. Now we can gather some details about our new partitioning and compare them with the information we collected at the beginning of this chapter:

```
df
```

Filesystem	1K-blocks	Used	Available	Use%	Mounted on
/dev/sda1	9859036	4224032	5234348	45%	/
varrun	95480	132	95348	1%	/var/run
varlock	95480	0	95480	0%	/var/lock
udev	10240	52	10188	1%	/dev
devshm	95480	0	95480	0%	/dev/shm
lrm	95480	17580	77900	19%	/lib/modules/2.6.17-10-generic/volatile

```
df -B 4k
```

Filesystem	4K-blocks	Used	Available	Use%	Mounted on
/dev/sda1	2464759	1056008	1308587	45%	/
varrun	23870	33	23837	1%	/var/run
varlock	23870	0	23870	0%	/var/lock
udev	2560	13	2547	1%	/dev
devshm	23870	0	23870	0%	/dev/shm
lrm	23870	4395	19475	19%	/lib/modules/2.6.17-10-generic/volatile

```
df -h
```

Filesystem	Size	Used	Avail	Use%	Mounted on
/dev/sda1	9.5G	4.1G	5.0G	45%	/
varrun	94M	132K	94M	1%	/var/run
varlock	94M	0	94M	0%	/var/lock
udev	10M	52K	10M	1%	/dev
devshm	94M	0	94M	0%	/dev/shm
lrm	94M	18M	77M	19%	/lib/modules/2.6.17-10-generic/volatile

```
fdisk -l
```

```
Disk /dev/sda: 10.7 GB, 10737418240 bytes
255 heads, 63 sectors/track, 1305 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes
```

Device	Boot	Start	End	Blocks	Id	System
/dev/sda1	*	1	1247	10016496	83	Linux
/dev/sda2		1248	1305	465885	5	Extended
/dev/sda5		1248	1305	465853+	82	Linux swap / Solaris

```
fdisk -s /dev/sda1
```

```
10016496
```

## 4 Merge Two ext3 Partitions

In this example I have my system partition `/dev/sda1` again (about 6GB of size) which is mounted by the partition `/dev/sda3` (about 4GB of size) on the hard disk. `/dev/sda3` is mounted to the `/data` directory and doesn't hold files needed by the Linux system, just user data. The current partitioning looks like this:

```
df -h
```

Filesystem	Size	Used	Avail	Use%	Mounted on
/dev/sda1	5.8G	4.1G	1.6G	73%	/
varrun	94M	132K	94M	1%	/var/run
varlock	94M	0	94M	0%	/var/lock
udev	10M	56K	10M	1%	/dev
devshm	94M	0	94M	0%	/dev/shm

```
lrm                94M   18M   77M  19% /lib/modules/2.6.17-10-generic/volatile
/dev/sda3          3.5G   72M  3.3G   3% /data
```

To merge `/dev/sda1` and `/dev/sda3`, we have to delete `/dev/sda3` and then enlarge `/dev/sda1` as described in chapter 3.

Now we open `/etc/fstab` and remove the line for `/dev/sda3` there if it exists:

```
vi /etc/fstab
```

The new file without `/dev/sda3` could look like this:

```
# /etc/fstab: static file system information.
#
#
proc          /proc          proc defaults    0 0
# /dev/sda1
UUID=566fd9e9-098f-4aae-9908-51efe171d8ba /              ext3 defaults,errors=remount-ro 0 1
# /dev/sda5
UUID=82102b65-35db-469a-9532-03d619d8cffb none          swap sw          0 0
/dev/hdc      /media/cdrom0  udf,iso9660 user,noauto    0 0
/dev/         /media/floppy0 auto rw,user,noauto 0 0
```

Then we unmount `/dev/sda3` and run `fdisk` to delete it. This can still be done on the original system as `/dev/sda3` doesn't contain system files:

```
umount /dev/sda3
```

```
fdisk /dev/sda
```

(Yes, it's `/dev/sda`, not `/dev/sda1`.)

The number of cylinders for this disk is set to 1305.

There is nothing wrong with that, but this is larger than 1024, and could in certain setups cause problems with:

- 1) software that runs at boot time (e.g., old versions of LILO)
- 2) booting and partitioning software from other OSs (e.g., DOS FDISK, OS/2 FDISK)

Type `m` to get a list of all commands:

Command (m for help): `m`

Command action

- `a` toggle a bootable flag
- `b` edit bsd disklabel
- `c` toggle the dos compatibility flag
- `d` delete a partition
- `l` list known partition types
- `m` print this menu
- `n` add a new partition
- `o` create a new empty DOS partition table
- `p` print the partition table
- `q` quit without saving changes
- `s` create a new empty Sun disklabel
- `t` change a partition's system id
- `u` change display/entry units
- `v` verify the partition table
- `w` write table to disk and exit
- `x` extra functionality (experts only)

Now let's delete `/dev/sda3`:

Command (m for help): `d`

*Partition number (1-5): 3*

Afterwards we write the new partition table to the disk:

*Command (m for help): w*

*The partition table has been altered!*

*Calling ioctl() to re-read partition table.*

*WARNING: Re-reading the partition table failed with error 16: Device or resource busy.*

*The kernel still uses the old table.*

*The new table will be used at the next reboot.*

*Syncing disks.*

Now we shut down the system:

```
shutdown -r now
```

and boot into our Knoppix Live-CD (or your rescue system). From here on the steps are identical to chapter 3, beginning with

```
su
```

```
umount /dev/sda1
```

so please refer to that chapter.

## 5 Links

- Knoppix: <http://www.knopper.net/knoppix-mirrors/index-en.html>